

Ubuntu - Extend Your Default LVM Space

So, like me, you installed Ubuntu and accepted the default use of lvm and now your operating volume is very small and the Ubuntu installer did not utilize the entire physical drive. There is a ton of free space that is not being utilized. And, possibly, your freshly installed cloud application (NextCloud) will soon exceed the allotted space within the first week or so as a result of data uploading or synchronization.

All credit goes to this article: <https://packetpushers.net/ubuntu-extend-your-default-lvm-space/>

```
$ df -h
```

Filesystem	Size	Used	Avail	Use%	Mounted on
tmpfs	791M	1.2M	790M	1%	/run
/dev/mapper/ubuntu--vg-ubuntu--lv	98G	7.0G	86G	8%	/
tmpfs	3.9G	0	3.9G	0%	/dev/shm
tmpfs	5.0M	0	5.0M	0%	/run/lock
/dev/sda2	2.0G	130M	1.7G	8%	/boot
tmpfs	791M	4.0K	791M	1%	/run/user/1000

```
user@svr1:~$ sudo vgdisplay
```

```
[sudo] password for user:
```

```
--- Volume group ---
VG Name          ubuntu-vg
System ID
Format          lvm2
Metadata Areas   1
Metadata Sequence No 2
VG Access        read/write
VG Status         resizable
MAX LV
Cur LV
Open LV
Max PV
Cur PV
Act PV
VG Size          <929.00 GiB
PE Size           4.00 MiB
Total PE          237823
Alloc PE / Size  25600 / 100.00 GiB
Free PE / Size   212223 / <829.00 GiB
VG UUID          rF3fw2-13h2-kAiL-aeWA-KyDZ-5HQU-GwvKDe
```

```
user@svr1:~$ sudo lvdisplay
```

```
--- Logical volume ---
LV Path          /dev/ubuntu-vg/ubuntu-lv
```

Last update: ubuntu_extend_default_lvm_space https://www.installconfig.com/doku.php?id=ubuntu_extend_default_lvm_space&rev=1688066189
2023/06/29 19:16

LV Name	ubuntu-lv
VG Name	ubuntu-vg
LV UUID	xUIxr-wnDl-7ZNk-EQpK-gAwb-Wug0-a7JSTb
LV Write Access	read/write
LV Creation host, time	ubuntu-server, 2023-06-28 23:21:26 +0000
LV Status	available
# open	1
LV Size	100.00 GiB
Current LE	25600
Segments	1
Allocation	inherit
Read ahead sectors	auto
- currently set to	256
Block device	253:0

```
user@svr1:~$ sudo su
root@svr1:/home/user# cd
root@svr1:~#
```

```
root@svr1:~# lvextend -l +100%FREE /dev/ubuntu-vg/ubuntu-lv
```

```
  Size of logical volume ubuntu-vg/ubuntu-lv changed from 100.00 GiB (25600
extents) to <929.00 GiB (237823 extents).
 Logical volume ubuntu-vg/ubuntu-lv successfully resized.
root@svr1:~#
```

Run lvdisplay once more to verify that that the logical volume was successfully resized.

```
root@svr1:~# lvdisplay
--- Logical volume ---
LV Path          /dev/ubuntu-vg/ubuntu-lv
LV Name          ubuntu-lv
VG Name          ubuntu-vg
LV UUID          xUIxr-wnDl-7ZNk-EQpK-gAwb-Wug0-a7JSTb
LV Write Access  read/write
LV Creation host, time  ubuntu-server, 2023-06-28 23:21:26 +0000
LV Status        available
# open           1
LV Size          <929.00 GiB
Current LE       237823
Segments         1
Allocation       inherit
Read ahead sectors  auto
- currently set to 256
Block device     253:0
```

```
root@svr1:~#
```

At this point you have increased the size of the block volume where your root filesystem resides, but

you still need to extend the filesystem on top of it.

First, run `df -h` to verify your (almost full) root file system, then run `resize2fs /dev/mapper/ubuntu-vg-ubuntu-lv` to extend your filesystem, and run `df -h` one more time to make sure you're successful.

Note: The following operations and output involves a 2TB physical drive instead of 1TB. Sorry, but this is a different server where the entire job was properly finished by extending the file system on top of the block volume that you just extended.

Here are the new readings for 'svr3' (using a pair of 2TB Drives on a hardware RAID-1 Array – which matters not.)

```
Logical volume ubuntu-vg/ubuntu-lv successfully resized.
root@svr3:~# lvdisplay
--- Logical volume ---
LV Path          /dev/ubuntu-vg/ubuntu-lv
LV Name          ubuntu-lv
VG Name          ubuntu-vg
LV UUID          0FjNEm-jrLm-tYwv-AzHT-TZmm-l9bx-aVWpyR
LV Write Access  read/write
LV Creation host, time ubuntu-server, 2023-06-18 18:42:52 +0000
LV Status        available
# open           1
LV Size          <1.82 TiB
Current LE       476287
Segments         1
Allocation       inherit
Read ahead sectors auto
- currently set to 256
Block device     253:0

root@svr3:~# df -h
Filesystem      Size  Used Avail Use% Mounted on
tmpfs           1.6G  1.2M  1.6G  1% /run
/dev/mapper/ubuntu--vg-ubuntu--lv   98G   12G   82G  13% /
tmpfs           7.8G    0   7.8G  0% /dev/shm
tmpfs           5.0M    0   5.0M  0% /run/lock
/dev/sda2        2.0G  253M  1.6G  14% /boot
tmpfs           1.6G   4.0K  1.6G  1% /run/user/1000
```

Now, run the following command to extend your filesystem.

```
root@nc3:~# resize2fs /dev/mapper/ubuntu--vg-ubuntu--lv
```

Results

```
resize2fs 1.46.5 (30-Dec-2021)
Filesystem at /dev/mapper/ubuntu--vg-ubuntu--lv is mounted on /; on-line
resizing required
old_desc_blocks = 13, new_desc_blocks = 233
```

Last update: ubuntu_extend_default_lvm_space https://www.installconfig.com/doku.php?id=ubuntu_extend_default_lvm_space&rev=1688066189
2023/06/29 19:16

The filesystem on /dev/mapper/ubuntu--vg-ubuntu--lv is now 487717888 (4k) blocks long.

Run df -h again.

```
root@nc3:~# df -h
Filesystem           Size  Used Avail Use% Mounted on
tmpfs                 1.6G  1.2M  1.6G  1% /run
/dev/mapper/ubuntu--vg-ubuntu--lv  1.8T   12G  1.8T  1% /
tmpfs                 7.8G    0  7.8G  0% /dev/shm
tmpfs                 5.0M    0  5.0M  0% /run/lock
/dev/sda2              2.0G  253M  1.6G  14% /boot
tmpfs                 1.6G  4.0K  1.6G  1% /run/user/1000
root@nc3:~#
```

Run vgdisplay again

```
root@nsrv3:~# vgdisplay
--- Volume group ---
VG Name               ubuntu-vg
System ID
Format                lvm2
Metadata Areas        1
Metadata Sequence No  3
VG Access             read/write
VG Status              resizable
MAX LV
Cur LV
Open LV
Max PV
Cur PV
Act PV
VG Size              <1.82 TiB
PE Size                4.00 MiB
Total PE              476287
Alloc PE / Size       476287 / <1.82 TiB
Free PE / Size        0 / 0
VG UUID               bK42QC-L9pu-bEiA-ndU0-j3v7-3XWU-tA06R5
```

Run lvdisplay again

```
root@svr3:~# lvdisplay
--- Logical volume ---
LV Path               /dev/ubuntu-vg/ubuntu-lv
LV Name               ubuntu-lv
VG Name               ubuntu-vg
LV UUID               0FjNEm-jrLm-tYWv-AzHT-TZmm-l9bx-aVWpyR
LV Write Access       read/write
LV Creation host, time ubuntu-server, 2023-06-18 18:42:52 +0000
```

```
LV Status           available
# open              1
LV Size             <1.82 TiB
Current LE          476287
Segments            1
Allocation          inherit
Read ahead sectors  auto
- currently set to 256
Block device        253:0
```

```
root@svr3:~#
```

VG Size and LV Size are both <1.82 TiB

I believe we're done here.

From:

<https://www.installconfig.com/> - Install Config Wiki

Permanent link:

https://www.installconfig.com/doku.php?id=ubuntu_extend_default_lvm_space&rev=1688066189

Last update: **2023/06/29 19:16**

